



# SZABO SCANDIC

Part of Europa Biosite

## Produktinformation



Forschungsprodukte & Biochemikalien



Zellkultur & Verbrauchsmaterial



Diagnostik & molekulare Diagnostik



Laborgeräte & Service

Weitere Information auf den folgenden Seiten!  
See the following pages for more information!



### Lieferung & Zahlungsart

siehe unsere [Liefer- und Versandbedingungen](#)

### Zuschläge

- Mindermengenzuschlag
- Trockeneiszuschlag
- Gefahrgutzuschlag
- Expressversand

### SZABO-SCANDIC HandelsgmbH

Quellenstraße 110, A-1100 Wien

T. +43(0)1 489 3961-0

F. +43(0)1 489 3961-7

[mail@szabo-scandic.com](mailto:mail@szabo-scandic.com)

[www.szabo-scandic.com](http://www.szabo-scandic.com)

[linkedin.com/company/szaboscandic](https://www.linkedin.com/company/szaboscandic) 



## Lass4 Blocking Peptide

### BACKGROUND

It is thought that Lass4 may be either a bona fide (dihydro)ceramide synthase or a modulator of its activity. When overexpressed in cells is involved in the production of sphingolipids containing different fatty acid donors (N-linked stearyl- (C18) or arachidoyl- (C20) ceramides) in a fumonisin B1-independent manner.

### ORDERING INFORMATION

**CATALOG NUMBER**  
X2299B

**SIZE**  
50  $\mu$ g

**CUSTOMER STORAGE**  
Product should be stored at -20°C.  
Aliquot to avoid freeze/thaw cycles

**FORMULATION**  
Provided as solution in phosphate buffered saline with 0.08% sodium azide

**SHIP CONDITIONS**  
Ship at ambient temperature, freeze upon arrival

**STABILITY**  
Products are stable for one year from purchase when stored properly

### COMMENTS

For use with Lass4 polyclonal antibodies (Cat. No. X2298P & X2300P).

### INSTRUCTIONS

Incubate antibody neat with at least a 50 fold stoichiometric excess of blocking peptide at 37 deg C for 20 minutes (molecular weights of peptide and antibody are ~2.5 kDa and ~160 kDa, respectively). Antibody can then be diluted to a concentration suitable for Western blot.

Example: 10  $\mu$ l or 10  $\mu$ g of Exalpha's rabbit anti-Lass4 (Cat. No. X2300P) is added to 10  $\mu$ g of blocking peptide for a total volume of 20  $\mu$ l. The mixture is allowed to incubate for 20 minutes at 37 deg C prior to dilution in suitable buffer (for Western blot, etc.).